



EZ3D

INSTALLATION/SOFTWARE/USAGE

Q: Question

How to make a template of a location/cycle?

A: Answer

There are two types of text file in the folder:

"C:\Users\Public\Documents\EZMetrology\EZ3D\Templates"

There is a template for the locations (*.loc). You can make a copy or create another text file "MyLocations.loc" and edit in notepad and create
"

Location 1

Location 2

Location 3

...

"

The other is a template for the cycles (*.tst), same procedure:

"

Initial

Hi load

Lo Load

....

"