



EZSLAM

INSTALLATION/SOFTWARE/USAGE

Q: Question

Is it OK for users to rename “EZSlam” folders?

A: Answer

Renaming could cause a reset of all settings/profiles and is maybe not the safest way forward as it can cause questions with respect to conventions etc.

One might also lose the screen layout settings, which will make the software look cumbersome and one might not recall how to clean up the layout.

We would, in exceptional cases, recommend to only rename the ‘data’ folder to separate projects and keep data sets completely separated.

EZSlam			
> This PC > Acer (C:) > Users > Public > Public Documents > EZMetrology > EZSlam			
☐ Name	Type	Date modified	Size
Archive	File folder	8/02/2018 11:12	
Calibration	File folder	8/02/2018 11:15	
Comparisons	File folder	8/02/2018 11:12	
Configurations	File folder	13/02/2018 10:58	
Data	File folder	13/02/2018 10:56	
Dump	File folder	13/02/2018 10:59	
Export	File folder	8/02/2018 11:12	
logos	File folder	8/02/2018 11:12	
Nominal	File folder	8/02/2018 11:13	
Reporting	File folder	8/02/2018 11:12	
WorkSpace	File folder	8/02/2018 11:12	
SessionListLayout.xml	XML Document	15/02/2018 10:48	6 KB
SessionMetricLayout.xml	XML Document	6/03/2018 08:27	4 KB
SessionRunLayout.xml	XML Document	6/03/2018 08:27	7 KB