



EZSLAM

INSTALLATION/SOFTWARE/USAGE

Q: Question

What is the meaning of a negative Overslam value?

A: Answer

The negative overslam is just an indication of the fact that at the given reference speed, the door does not even close.

By conclusion, it means there is a lot of resistance. If it happens on occasion, that's a local effect. If it happens too often, one might reconsider increasing the reference speed.

While it doesn't change anything in the analysis -a negative value is simply indicating the door is hard to close- it might be hard to envision to have a 'negative' overslam. The result should therefore not necessarily be taken literally.